# Jeevan Pramaan Face App 3.6

#### Minimum Requirements for Mobile Phones to run Jeevan Pramaan face application


- 1. Android 7.0 (SDK 24) or greater
- 2. RAM 4+ GB
- 3. Storage 64 GB (Minimum 500 MB free storage space)
- 4. Camera Resolution 5MP or greater
- 5. Face RD Service (AadhaarFaceRd)

Note: Android OS--However, rooted mobiles, where OS of the mobile has been changed, cannot be used.


#### **Download & Installation**

1. The user also needs to install the Face RD Service provided by UIDAI. It is available on play store as shown below:

https://play.google.com/store/apps/details?id=in.gov.uidai.facerd



After the Rd service is installed it will be visible in Settings→ App Info as shown in screenshot below:




2. The link to download the Jeevan Pramaan Face application will appear along with other Jeevan Pramaan Applications as shown below.

<u>https://jeevanpramaan.gov.in</u> → Download

Digital Life Certificate for Pensioners.	Skip to main content 🛛 Search Here 🔽 🔍 A- A A+ 🔊 🗖 🕈 🗖 🖬 🗳 40 हिन्दी
Jeevan Pramaan	Home About Get a certificate Locate a Centre Download Guidelines Circular FAQ PDA/PSALogin
	Download Application
	For Windows and Android Operating System
You can download the Jeevan Pramaan Windows & Ar client software here. The client software will help perfor registration for a life certificate, for authentication if will Adahaar Biometric Authentication platform. To start the download please provide your e-mail in the The download link will be made available after submitti e-mail address. The client software is intended to be used only for Pen life certificate registration. Usage of the application for other purpose is prohibited.	m a use the Jeevan Pramaan 3.6 Installer form. Jeevan Pramaan 3.5 Installer Ig your Client Installation Document 3.5 sioner's BD/Benilstered Device) Service & Drivers for Windows
Download Documents	Jeevan Pramaan 3.6 Android App
Client Installation Document 3.5 RD(Registered Device) Service & Drivers for Window	RD(Registered Device) Service & Drivers for Android
Client Installation Document for Face APP	Mobile Face App Download
** The client software will require a biomatric fingerprint/ in: device. In case you require support please contact our hely jeevanpramaan[at]gov[dot]in.	

### Jeevan Pramaan Face App


Now as you run the Jeevan Pramaan Face Application the following pop-up is shown, Click on yes:




As you proceed to Authentication the following pop-up is shown, Click on yes if you want to proceed towards Face Scan based Authentication:

2:26 🖨		2.	78 <b>Hall 💎</b>	739	% 🚍	
Jee						
	Operator	Authe	nticatio	n		
Full Name as in Aadhaar neha						
1 44		6 - 6				
	ne holder		adnaa	r, ner	eby ie	
	e Scan				ic Al	
Do y	ou want to s	scan Fac	e?		Fe	
			NO	YES	'e ic	
		0.000	marca			
			Scan			
				_		
4						


After that you need to allow the permissions shown below in order to proceed further:



The following Guidelines are shown while proceeding towards Face Scan, click on proceed to move towards Face Scan Authentication.



Now while Face Authentication keep your face straight and follow the instructions shown on screen:



# For proper results ensure:

**1. Position**: For capturing facial image, it is advisable that adjust the camera at the right distance or in the right posture.

2. Frontal pose needs to be captured i.e. no head rotation or tilt. The Pensioner should be instructed to be seated properly with their back upright and their face towards the camera.

3. It is strongly recommended that the face should be captured with neutral (non-smiling) expression, teeth closed, and both eyes open and looking into the camera.

4. **Illumination**: Poor illumination has a high impact on the performance of face recognition. Proper and equally distributed lighting mechanism should be used such that there are no shadows over the face, no shadows in eye sockets, No light exactly above the ,can cause shadows. Light should be diffused and placed in front of the Pensioner so that there are no shadows under the eye.

5. **Eye Glasses**: If the person normally wears glasses, it is recommended that the photograph be taken with glasses. However, the glasses should be clear and transparent. Dark glasses /tinted glasses should be taken off before taking the photograph.

## Some of the actionable feedbacks in software are:

- 1. No face Found
- 2. Enrolee too far
- 3. Pose (Look Straight)
- 4. Insufficient lighting
- 5. Very low face confidence
- 6. Non-uniform lighting (of face in output image)
- 7. Incorrect background (in output image)
- 8. Insufficient lighting (bad grey values in face area of output image)